

## Workflow 1: Attaching CFLHD Cell Libraries

1. For CFLHD consultants, begin by downloading *V8\_Resource.zip* from the CFLHD web site. As the cell libraries are specific to CFLHD projects, the user should leave the libraries in the *V8\_Resource\X\_30\Standards\Cell\_lib* directory.
2. From the MicroStation drop down menu's, select *Element>Cells*.




Figure 8-1: Element Menu

3. The cell library palette will now be accessible. Select *File>Attach*, and navigate to the correct cell library.




Figure 8-2: Cell Library Dialog Box



Once selected, the cells will be visible in the windows on the Cell Library palette.




Figure 8-3: Populated Cell Library Dialog Box